

# Transmitter Firmware – Change Notes

21.01.2025

The changes applied to transmitter firmware and corresponding versioning are as followed. please be noted that these updates, enhancement or fixes have no impact on the measurement result.

**M300 (PN: 30280770, 30280772, 30280771, 30280773, 30280776, 30280778, 30280777, 30280779, 30280774, 30280775)**

FW Version	Release Date	Description
V1.2.00	2023/Jul/19	<ul style="list-style-type: none"><li>Added: NextGen ISM pH/ORP sensors related new functions</li></ul>
V1.1.03	2019/Dec/02	<ul style="list-style-type: none"><li>Improvement: on M300 Water power voltage to be fixed to -675mV for analog O<sub>2</sub> low sensor</li><li>Improvement: the holding time setable with the range of "20 seconds~8m units"</li></ul>
V1.1.02	2019/Apr/18	<ul style="list-style-type: none"><li>Bug fixed: conductivity temperature compensation for all non-linear change</li></ul>
V1.1.01	2018/Aug/15	<ul style="list-style-type: none"><li>Added: %NaOH calculation to read 0.00% for all calculated values below 0.1%</li><li>General bug fixed</li></ul>
V1.1.00	2017/May/31	<ul style="list-style-type: none"><li>Added: USB Data Logging&amp;Configuration functions</li><li>Added: alarm for wrong date/time</li><li>Added: "pO<sub>2</sub>" (O<sub>2</sub> partial pressure) readability in mbar</li></ul>